## Migrating existing Paramount™ sample sets from Hauptwerk 4™ to Hauptwerk V™.

- 1. Using Hauptwerk 4 make a BACKUP of all your settings DO NOT OMIT THIS STEP
- 2. Download the Hauptwerk User Guide for Hauptwerk V for future reference: https://www.hauptwerk.com/documentation/
- 3. Ensure that you have Hauptwerk V installed and fully working test with the St Anne's organ
- 4. WARNING DO NOT migrate your Paramount sample sets if you're using a trial version of Hauptwerk V and may subsequently revert to Hauptwerk 4. Paramount Organ Works™ accepts no responsibility if you lose your existing Hauptwerk 4 licenses from your Hasp dongle
- 5. Ensure that you have your HW4 Hasp key plugged in as well as your iLok dongle
- 6. Select the **File** menu option 'Initiate migration of Hauptwerk pre-v5 sample set licenses to this version ...'
- 7. Save the data file to the desktop
- 8. Follow the on-screen link for the form to <a href="https://www.hauptwerk.com/prev5licensemigrations/">https://www.hauptwerk.com/prev5licensemigrations/</a>
- 9. Enter all the requested data into the on-screen form, including selecting the migration file from your desktop, then submit the form
- 10.License(s) will appear in the iLok License Manager
- 11. Activate the license(s) within iLok
- 12. Download the Hauptwerk licensing packages file from: <a href="https://www.hauptwerk.com/licensingpackages/">https://www.hauptwerk.com/licensingpackages/</a> and save it to the desktop
- 13. Select the File menu option 'Install ...' and install the licensing packages file
- 14. Select the **File** menu '**Restore** ...' to restore the settings backup that you made at stage 1
- 15. Using your browser, visit: <a href="http://www.paramountorganworks.com">http://www.paramountorganworks.com</a> and click the Downloads tab at the bottom of the Home screen
- 16. Download all of your current Paramount sample sets, using the links provided and save them to the desktop
- 17. Select the Hauptwerk V **File** menu '**Install ...**' to install each of your downloaded sample sets
- 18. For the P310/P320/P332/P450 series ensure that you install in that order Paramount 310 first followed by any further sample sets that you have. You do not need to do this for the Paramount 341
- 19. Remove your old Hauptwerk 4 Hasp dongle